

⚠ Hors période de menstruations

☐ **Chlam / Gono seuls.** Utiliser le milieu suivant pour le prélèvement :



Aptima bouchon blanc


☐ **Autres cas.** Utiliser le milieu suivant pour le prélèvement :



Swab bouchon violet



1. Lavez-vous les mains soigneusement.




6. En tenant toujours l'écouvillon, dévisser le bouchon du tube et placer l'écouvillon dans le tube. **Ne pas renverser le liquide contenu dans le tube*.**

*** Dans ce cas, demandez un nouveau kit au laboratoire**



2. Ouvrir partiellement le sachet et retirer le tube. Prenez l'écouvillon présent dans le sachet **sans toucher le coton de l'écouvillon*** → le tenir par la tige.


*** Dans ce cas, demandez un nouveau kit au laboratoire**



7. Casser la tige à hauteur du repère de couleur noire en la pressant contre le bord du tube.



3. Tenez l'écouvillon par la tige entre l'index et le pouce au-dessus du repère de couleur noir.



8. Revissez fermement le bouchon sur le tube.

Inscrire sur le tube votre **Nom, Prénom, date de naissance** et **heure de prélèvement**.



4. Prendre la position utilisée pour mettre un tampon et introduire doucement l'écouvillon dans le vagin par la partie coton sur une distance d'environ 5 cm.

Placer le tube dans le sachet puis le sceller. Insérer cette fiche après l'avoir complétée ainsi que l'ordonnance dans la poche latérale du sachet. **Conserver le prélèvement à température ambiante et le déposer au laboratoire dans les meilleurs délais, 24h maximum.**



5. Faites tourner doucement l'écouvillon dans le sens des aiguilles d'une montre **pendant 30 secondes**. Retirer l'écouvillon du vagin sans toucher la peau.

Nom usuel :

Date de prélèvement :

Nom de naissance :

Heure de prélèvement :

Prénom :

Self-collected vaginal specimen
Classic germs, PCR *Chlamydia trachomatis*/gonocoque PCR
Mycoplasma genitalium PCR – *Trichomonas vaginalis* PCR – *U. urealyticum* PCR

⚠ Outside the menstrual period

☐ **Chlam / Gono only**. Use the following tube for the sample :



Aptima - White cap

☐ **Others**. Use the following tube for the sample :



Swab - Purple cap

	1. Wash your hands carefully.
	2. Partially open the pouch and remove the tube. Take the swab from the pouch without touching the swab tip* → Hold the swab by the shaft. <i>* In that case, ask the laboratory for a new kit</i>
	3. Hold the swab by the shaft between your thumb and index finger, above the black marking.
	4. Assume the same position you would use to insert a tampon. Gently insert the swab, cotton tip first, approximately 5 cm into the vagina.
	5. Gently rotate the swab clockwise for 30 seconds. Carefully withdraw the swab without allowing it to touch the skin.
6. While continuing to hold the swab, unscrew the tube cap and place the swab into the tube. Do not spill the liquid contained in the tube* <i>* In that case, ask the laboratory for a new kit</i> 7. Break the swab shaft at the black marking by pressing it against the rim of the tube. 8. Screw the tube cap back on tightly. Write your last name, first name, date of birth, and the time of specimen collection on the tube. Place the tube into the pouch and seal it. After completing this form, insert it together with the prescription into the side pocket of the pouch. Store the specimen at <u>room temperature</u> and deliver it to the laboratory as soon as possible, <u>within 24 hours</u> of collection. Last name : Birth name : First name : Date of birth : Sampling time :	